配置文件位于站点根目录下的 data/config.php，用户名、密码保存在这个配置文件中，如果忘记了用户名、密码可以查看这个文件，如果需要重新设置用户名、密码，可以将 data/config.php删除，然后重新初始化。

如果您使用的Nginx，请务必将以下规则添加到站点配置中，否则数据库可能被下载（非常危险）：

如果使用得Apache则无需设置，已内置.htaccess进行屏蔽。
如果您使用的Docker安装也无需此配置，默认已内置规则
如果使宝塔一键安装用户，不需要此设置

其他说明

配置文件说明

安全设置

#安全设置
location ~* ^/(class|controller|db|data|functions|templates)/.*.(db3|php|php5|sql)$ { return 403;
}
location ~* ^/(data)/.*.(html)$ {
deny all;
}
location /db {
deny all;
}

#伪静态
rewrite ^/click/(.*) /index.php?c=click&id=$1 break;
rewrite ^/api/(.*)?(.*) /index.php?c=api&method=$1&$2 break; rewrite /login /index.php?c=login break;

Nginx反向代理

如果您使用的Docker部署，需要通过域名进行访问，您可以通过下面2个方法完成：

1. 直接将域名解析到您服务器IP，然后访问 http://域名:端口进行访问
2. 如果您不希望带上容器端口，也可以通过Nginx反向代理绑定域名进行访问

Nginx反向代理配置参考：

server {
listen 80;

#改成你自己的域名
server_name demo.onenav.top;

#指定网站日志路径
#access_log /data/logs/demo.onenav.top_nginx.log xlog;
charset utf-8,gbk;

location / {
proxy_connect_timeout 10;
Default is HTTP/1, keepalive is only enabled in HTTP/1.1 proxy_http_version 1.1;
proxy_set_header Connection "";
#chunked_transfer_encoding off;
proxy_set_header Host $host;
#将3080改成你容器的端口
proxy_pass http://127.0.0.1:3080;
proxy_set_header X-Real-IP $remote_addr;
proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
}
}

版本号 #44
由 xiaoz 创建于 7 八月 2021 03:03:35
由 xiaoz 更新于 28 十一月 2024 07:48:06